### Ruta de actualización de versiones:

#### 🕏 Note

- Installation files for 32-bit operating systems are not provided from BioStar 2.9.2.
- Do not install BioStar 2 on a PC where BioStar 1 is installed. This may cause performance problems.
   If BioStar 2.3.0 is installed on top of a BioStar 2.2.1 or 2.2.2 installation, all information stored in the SQLite database is migrated to a new MariaDB database.
- igher. If the installed version is lower than 2.6.0, installing all versions in a

Current Version	Upgrade Path
2	2.2.1 > 2.3 > 2.4 > 2.4.1 > 2.5.0 > 2.6.4 > Latest Version
2.2 2.2.1 2.2.2	2.3 > 2.4 > 2.4.1 > 2.5.0 > 2.6.4 > Latest Version
2.3	2.4 > 2.4.1 > 2.5.0 > 2.6.4 > Latest Version
2.4	2.4.1 > 2.5.0 > 2.6.4 > Latest Version
2.5 2.6	2.6.4 > Latest Version
2.6.4 or higher	Latest Version

#### BioStar 2.9.3

#### New and improved features

Category	Functionality
General	<ul> <li>Added REPORT feature related to access control events</li> <li>Updated German, French, Romanian, Russian, Polish, Czech, Greek, and Italian resource files</li> </ul>
Device	<ul> <li>Supports keypad Backlight of XPass D2</li> <li>Supports QR code authentication in BioStation 3</li> </ul>
Setting	<ul> <li>Added CARD PRINTER feature</li> <li>Added SYSTEM BACKUP and RESTORE feature</li> <li>Stabilization of 'Specific Devices' Automatic User Synchronization option</li> </ul>

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later
- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.7.1 or later
- FaceStation 2: 1.5.3 or later
- CoreStation: 1.6.1 or later
- BioEntry P2: 1.4.4 or later .

- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.5.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.7.1 or later
- FaceLite: 1.3.4 or later
- XPass 2: 1.3.2 or later
- FaceStation F2: 2.1.3 or later
- X-Station 2: 1.2.2 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later
- BioStation 3: 1.1.0 or later

#### New and improved features

Category	Functionality
Setting	- Improved security of login password vulnerabilities for brute-force attack

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later
- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.7.1 or later

- FaceStation 2: 1.5.3 or later
- CoreStation: 1.5.3 or later
- BioEntry P2: 1.4.4 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.5.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.7.0 or later
- FaceLite: 1.3.4 or later
- XPass 2: 1.3.2 or later
- FaceStation F2: 2.1.2 or later
- X-Station 2: 1.2.0 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later
- BioStation 3: 1.0.2 or later

### New and improved features

Category	Functionality
General	<ul> <li>Adopted Improved Visual Face Algorithm</li> </ul>
User	<ul> <li>Added Visual Face Import</li> <li>Added Visual Face Migration</li> <li>Added User Configuration Partial Update</li> </ul>
Device	<ul> <li>Supports BioStation 3 (BS3-DB, BS3-APWB)</li> <li>When a sync error occurs because of exceeding the maximum number of users or credentials in the device, the error message explains the reason for the sync error.</li> </ul>

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later

- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later
- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.7.1 or later
- FaceStation 2: 1.5.3 or later
- CoreStation: 1.5.3 or later
- BioEntry P2: 1.4.4 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.5.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.7.0 or later
- FaceLite: 1.3.4 or later
- XPass 2: 1.3.2 or later
- FaceStation F2: 2.1.2 or later
- X-Station 2: 1.2.0 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later
- BioStation 3: 1.0.2 or later

New and improved features

Category

Functionality

### General

Adopted Improved Visual Face Algorithm

### User

- Added Visual Face Import
- Added Visual Face Migration
- Added User Configuration Partial Update

### Device

- Supports BioStation 3 (BS3-DB, BS3-APWB)
- When a sync error occurs because of exceeding the maximum number of users or credentials in the device, the error message explains the reason for the sync error.

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later
- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later

- BioEntry W2: 1.7.0 or later
- FaceStation 2: 1.5.2 or later
- CoreStation: 1.5.2 or later
- BioEntry P2: 1.4.3 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.5.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.6.0 or later
- FaceLite: 1.3.2 or later
- XPass 2: 1.3.1 or later
- FaceStation F2: 2.0.3 or later
- X-Station 2: 1.1.3 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later

New and improved features

Category

Functionality

Time & Attendance

- Supports setting the storage period of punch logs
- Improved security vulnerabilities

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later
- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.1 or later
- CoreStation: 1.5.2 or later
- BioEntry P2: 1.4.3 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.1 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.6.0 or later
- FaceLite: 1.3.2 or later
- XPass 2: 1.2.4 or later
- FaceStation F2: 2.0.3 or later
- X-Station 2: 1.1.3 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later

New and improved features

Category

Functionality

General

- Added visual face to the dashboard
- Added setting.config file initialization logic
- Added procedure to accept to collection and use of the privacy when using cloud
- Updated German and French resource files

User

- Improved the visual face mobile enrollment usability
- Improved the user interface of Visual Face Mobile Enrollment page
- Added footer to email sending the visual face mobile enrollment link
- Added Error\_Description column to user list file that failed CSV import
- Added Hide Face Credential Preview Image option
- Added the Use QR as card option

Device

Improved USB Device Agent security vulnerabilities

- Supports setting the byte order for smart cards
- Allows connecting X-Station 2 as a slave device of CoreStation

# Door

- Added relay deactivation option for exit button input
- Added 'All Devices' option to dual authentication setting to door

# Zone

Improved occupancy limit zone monitoring page

# Monitoring

- Separated the log related to door unlock
- Door Unlocked (Exit Button)
- Door Unlocked (By Operator)

# Video

Improved security vulnerabilities

# Setting

- Added option to delete unassigned card
- Support to log in to BioStar 2 with Active Directory account

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.1 or later

- BioStation A2: 1.9.1 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.1 or later
- CoreStation: 1.5.2 or later
- BioEntry P2: 1.4.3 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.1 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.6.0 or later
- FaceLite: 1.3.2 or later
- XPass 2: 1.2.4 or later
- FaceStation F2: 1.1.4 or later
- X-Station 2: 1.1.3 or later
- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later

New and improved features

Category

Functionality

# General

• Applied Log4j 2 v2.17.1

# Setting

• Stabilization of features for automatic user synchronization

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.0 or later
- BioStation A2: 1.9.0 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.1 or later
- CoreStation: 1.5.2 or later
- BioEntry P2: 1.4.3 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.1 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.5.0 or later
- FaceLite: 1.3.1 or later
- XPass 2: 1.2.4 or later
- FaceStation F2: 1.1.2 or later
- X-Station 2: 1.1.2 or later

- OM-120: 1.2.1 or later
- Secure I/O 2: 1.3.1 or later
- DM-20: 1.2.2 or later
- IM-120: 1.0.0 or later

New and improved features

Category

Functionality

### General

- Supports OpenJDK
- Applied Log4j 2 v2.16.0
- Improved security vulnerabilities
- Updated APIs in Swagger
- Improved the server performance
- Improved the performance of processing data on the database
- 26 bit Wiegand card option support for BioStar 1.x to BioStar 2.x Migration Tool

User

Supports PIN enrollment via CSV Import

# Device

- Supports Input Module (IM-120)
- Supports 1:N security level setting for CoreStation
- Improved the speed of connecting devices

# Door

Changed the default value of held open setting

# Access Control

Improved the speed of linking access groups

# Monitoring

- Improved event log processing performance
- Improved the speed of accessing the monitoring menu

# Setting

Stabilization of features for automatic user synchronization

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.0 or later
- BioStation A2: 1.9.0 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.0 or later

- CoreStation: 1.5.2 or later
- BioEntry P2: 1.4.2 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.1 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.5.0 or later
- FaceLite: 1.3.0 or later
- XPass 2: 1.2.4 or later
- FaceStation F2: 1.1.2 or later
- X-Station 2: 1.1.0 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.1 or later
- IM-120: 1.0.0 or later

New and improved features

Category

Functionality

Time & Attendance

Created the T&A report inquiry API

- Supports private SSL certificates with a passphrase
- Changed the TLS default version to 1.2
- Updated T&A APIs in Swagger
- Improved of the T&A report inquiry performance

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.0 or later
- BioStation A2: 1.9.0 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.0 or later
- CoreStation: 1.5.1 or later
- BioEntry P2: 1.4.1 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.5.0 or later
- FaceLite: 1.3.0 or later
- XPass 2: 1.2.3 or later
- FaceStation F2: 1.1.1 or later
- X-Station 2: 1.1.0 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.1 or later

New and improved features

Category

Functionality

Device

Supports X-Station 2 Fingerprint model (XS2-ODPB, XS2-OAPB)

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.10.0 or later
- BioStation A2: 1.9.0 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.5.0 or later

- CoreStation: 1.5.1 or later
- BioEntry P2: 1.4.1 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.4.0 or later
- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.5.0 or later
- FaceLite: 1.3.0 or later
- XPass 2: 1.2.3 or later
- FaceStation F2: 1.1.1 or later
- X-Station 2: 1.0.3 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.1 or later

New and improved features

Category

Functionality

General

- Updated APIs in Swagger
- Updated a Japanese resource file

### User

### Supports a new credential

- QR/Barcode

#### Device

Supports X-Station 2 (XS2-QDPB, XS2-QAPB, XS2-DPB, XS2-APB)

#### Zone

Supports Occupancy Limit Zone

# Setting

Separated email settings of both Visual Face Mobile Enrollment and QR

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.9.0 or later
- BioStation A2: 1.8.0 or later
- BioStation L2: 1.6.1 or later
- BioEntry W2: 1.6.3 or later
- FaceStation 2: 1.4.2 or later
- CoreStation: 1.5.1 or later
- BioEntry P2: 1.4.1 or later
- BioEntry R2: 1.4.1 or later
- BioLite N2: 1.3.2 or later

- XPass D2: 1.3.2 or later
- XPass D2 (Rev 2): 1.5.0 or later
- FaceLite: 1.2.0 or later
- XPass 2: 1.2.3 or later
- FaceStation F2: 1.0.5 or later
- X-Station 2: 1.0.1 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.1 or later

New and improved features

Category

Functionality

### General

- Supplementation of New Local API
- Updated a German resource file

#### User

- Supports a drag & drop method when registering Visual Face with 'Upload Image'
- Provides guidance on success or failure of Visual Face Mobile Enrollment

Supports new Date File Export/Import

# Device

- Added minimum threshold temperature setting function on the thermal camera
- Supports Intelligent Slave
- Screen saver option support for FaceStation 2, FaceStation F2

# Setting

Improved Email Settings

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.9.0 or later
- BioStation A2: 1.8.0 or later
- BioStation L2: 1.6.0 or later
- BioEntry W2: 1.6.2 or later
- FaceStation 2: 1.4.0 or later
- CoreStation: 1.4.1 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.2 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.2 or later
- FaceLite: 1.2.0 or later
- XPass 2: 1.2.2 or later

- FaceStation F2: 1.0.2 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

Category

Functionality

### General

Updated some language resource files

User

- Displays user information on the Mobile Access Cards
- Provides a guide on the screen when registering Visual Face on the mobile device

# Time & Attendance

Improves server synchronization structure

# Setting

Stabilization of features for Mobile Access

- Supports Dynamic site
- Improves a user interface

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.9.0 or later
- BioStation A2: 1.8.0 or later
- BioStation L2: 1.6.0 or later
- BioEntry W2: 1.6.1 or later
- FaceStation 2: 1.4.0 or later
- CoreStation: 1.4.1 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.2 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.2 or later
- FaceLite: 1.2.0 or later
- XPass 2: 1.2.2 or later
- FaceStation F2: 1.0.1 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

Category

Functionality

# General

- BioStar 2 performance improvements
- Supplementation of New Local API

#### User

Supports batch registration of Visual Face using CSV import

#### Device

Stabilization of features for thermal camera

# Monitoring

Supports thermal report

# Time & Attendance

Fixed bugs of some features in the TIME ATTENDANCE menu

# Setting

- Email contents improvements
- Stabilization of 'Specific Devices' Automatic User Synchronization option

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.9.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.6.0 or later
- BioEntry W2: 1.6.0 or later
- FaceStation 2: 1.4.0 or later
- CoreStation: 1.4.1 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.2 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.2 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.2 or later
- FaceStation F2: 1.0.0 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

### Category

# Functionality

# Device

- Supports server matching on FaceStation 2
- Supports thermal camera on face authentication devices
- Support FaceStation F2
- Support BioEntry W2 (Rev 2)

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.6.0 or later
- BioEntry W2: 1.5.0 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.4.0 or later
- BioEntry P2: 1.4.0 or later

- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.1 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.1 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.1 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

Category

Functionality

# Time & Attendance

- Supports Wiegand devices
- Improved the Individual Report usability
- Supports users to update TA reports

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.6.0 or later
- BioEntry W2: 1.5.0 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.4.0 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.1 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.1 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.1 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

# Category

# Functionality

# General

- Supplementation of New Local API
- Improvement of backup and recovery logic for Web-App, CGI server system.conf
- Exclusion of TLS V1.1 for improved security
- Improved Thrift communication logic log
- Improved security vulnerabilities on Redis

### User

- Improved the logic for issuing mobile access cards
- Improved the logic for issuing mobile access cards using the CSV

### Setting

Stabilization of features for mobile access cards

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.5.1 or later

- BioEntry W2: 1.5.0 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.4.0 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.1 or later
- XPass D2: 1.3.1 or later
- XPass D2 (Rev 2): 1.4.1 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.1 or later
- OM-120: 1.2.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

Category

Functionality

General

Updated language resource files

Device

- Supports FaceStation 2 and FaceLite as a slave of CoreStation
- Supports Mobile Access on BioLite N2

# Elevator

Improved the scheduled unlock zone function to support elevator

# Setting

Supports Zone in the Admin Item Settings of the custom level

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.4.0 or later
- BioEntry P2: 1.4.0 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.3.0 or later
- XPass D2: 1.3.0 or later
- XPass D2 (Rev 2): 1.4.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.1 or later

- OM-120: 1.1.0 or later
- Secure I/O 2: 1.3.0 or later
- DM-20: 1.2.0 or later

New and improved features

Category

Functionality

General

Fixed local file inclusion (LFI) vulnerability

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later

- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.3.1 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.3.0 or later
- XPass D2 (Rev 2): 1.4.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

General

Supports MS SQL Server 2019

### Time & Attendance

Move the 'In/Out Only and 'All Punches' options in the Individual Report

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.1 or later
- CoreStation: 1.3.1 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.4.0 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.3.0 or later
- XPass D2 (Rev 2): 1.4.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.2.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

General

DB encryption to enhance security on personal information

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.0 or later
- CoreStation: 1.3.1 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.3.1 or later

- BioLite N2: 1.2.0 or later
- XPass D2: 1.2.0 or later
- XPass D2 (Rev 2): 1.4.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

General

- Supports Windows Authentication for MS SQL database server connections
- Supports MS SQL Server 2017
- Added the Floor Control API to BioStar 2 API Documents

Device

Support XPass D2(Rev 2)

Setting

- Enhancement in Mobile Access usage
- Stabilization of 'Specific Devices' Automatic User Synchronization option

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.1 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.0 or later
- CoreStation: 1.3.1 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.3.1 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.2.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

Time & Attendance

Support to generate TA reports simultaneously on multiple clients

### Setting

- Added the new Suprema Mobile Access
- Stabilized 'Specific Devices' Automatic User Synchronization option

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.0 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.0 or later

- CoreStation: 1.3.1 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.3.1 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.2.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

General

Improved dashboard usability

User

Added User IP item to User Information

Device

Supports the alert sound for 'Input(Event Name Change)' in the <Trigger & Action>

# Monitoring

Supports the sorting of lists for the User ID and User Group column of the <Muster</li>
 Status> page

# Setting

# Enhances the system security

 Added 'Specific Devices(Only devices belonging to the access group)' option to <Automatic User Synchronization>

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.0 or later
- BioStation L2: 1.5.1 or later
- BioEntry W2: 1.4.1 or later
- FaceStation 2: 1.3.0 or later
- CoreStation: 1.3.0 or later
- BioEntry P2: 1.3.1 or later
- BioEntry R2: 1.3.1 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.2.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.1.0 or later

- OM-120: 1.1.0 or later .
- Secure I/O 2: 1.2.4 or later .
- DM-20: 1.1.5 or later

New and improved features

Category

Functionality

### Device

- Support FaceLite
- Support XPass 2

Time & Attendance

- Improve the Custom Level
- Support to use the custom user field in the T&A report .
- Supports the sorting for entire data in the T&A report
- Added option to select 'First in & Last Out' or 'All in/Out Punches' to search conditions of the individual report

Visitor

Support to the USB fingerprint scanner connection (BioMini, BioMini Plus, BioMini Plus 

2)

### Setting

- Update the resource files of Japanese, Arabic, and Spanish
- Add Automatic backup function for Setting.conf file

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.8.0 or later
- BioStation A2: 1.7.0 or later
- BioStation L2: 1.5.0 or later
- BioEntry W2: 1.4.0 or later
- FaceStation 2: 1.3.0 or later
- CoreStation: 1.3.0 or later
- BioEntry P2: 1.3.0 or later
- BioEntry R2: 1.3.0 or later
- BioLite N2: 1.2.0 or later
- XPass D2: 1.2.0 or later
- FaceLite: 1.1.0 or later
- XPass 2: 1.0.1 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.5 or later

# New and improved features

Category

Functionality

#### Device

- Supports multiple use function of controllers in CoreStation
- Supports options for selection by card type
- Supports the fingerprint/face duplicate check
- Supports Anti-Tailgating
- Supports setting options for Wiegand authentication result output

### Door

Supports Anti-Tailgating

#### Visitor

Supports to search option for visitors using fingerprints

# Setting

- Supports user group synchronization in Active Directory
- Supports Anti-Tailgating

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.1 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.5.0 or later
- BioEntry W2: 1.4.0 or later
- FaceStation 2: 1.2.1 or later
- CoreStation: 1.3.0 or later
- BioEntry P2: 1.3.0 or later
- BioEntry R2: 1.3.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.2.0 or later
- FaceLite: 1.0.0 or later
- XPass 2: 1.0.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

## Category

## Functionality

## General

Change the license policy

## Visitor

Add the VISITOR menu

### Setting

Add the settings for visitor management

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.1 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.1 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later

- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

Functionality

General

Add BioStar 1.x to BioStar 2.x Migration Tool

Monitoring

Support to the Clear APB for each user

# Setting

- Add the event items to IMAGE LOG menu
- Add the encryption option to Active Directory menu
- Supports that the administrator can change the port 9000 in FastCGI of Port menu

### Compatible firmware

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.1 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.1 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

BioStar 2.7.5

New and improved features

## Category

## Functionality

## User

Support to the list sorting for group and status column

## Device

- Support to the list sorting for RS-485 column
- Remove the unsupported AoC events
- Added an Ambient Brightness option to the FaceStation 2 slave device

## Door

Support to the list sorting for group column

## Video

Remove the unsupported AoC events

### Setting

- Add the Active Directory menu
- Supports that the administrator can change the port 9000 in setting.conf
- Remove the unsupported AoC events

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later

- BioStation 2: 1.7.1 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.1 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

Functionality

Device

Support for Quick Enrollment for FaceStation 2

(FaceStation 2 FW V1.2.2 or later)

## Setting

- Limits the use of passwords that contain the same string, consecutive string, and login
- ID
- Limits reuse of the same password
- Support to Spanish and Arabic
- Expanding the number of custom levels to unlimited

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.1 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.1 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

#### Functionality

### Device

Increase the number of administrators that can be added per device

• Change the way new settings are applied when adding administrators using batch edit of devices

#### Setting

Support for reconnection of devices configured as a port forwarding

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.0 or later
- BioStation A2: 1.6.0 or later

- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.0 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

Functionality

# Monitoring

- Support to Live Video View on Graphic Map
- Support to viewing Anti-passback Zone and Fire Alarm Zone on Graphic Map

Time & Attendance

Supports <Allowed a day before/after time> setting for working 24 hours or longer

## Setting

- Add the Security menu
- Change Password Level options
- Support to the setting for Maximum Password Age and Maximum Password Change
   Limit
- Support to the setting options for password failures at login
- Support to the Storage Path Settings for image logs

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.0 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.0 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

Functionality

Device

- Support to Input(Event Name Change) in Trigger & Action
- Support to the OM-120 Relay time setting value from 1 second

User

Support for deleting users stored on the device

# Monitoring

Provides the log about whether a user has been updated on the device or the server

# Setting

- Supports synchronization of all devices connected to the server when users update the device
- Adds root password verification procedures during installation and upgrade

### Compatible firmware

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.0 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.0 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

BioStar 2.7.0

New and improved features

## Category

## Functionality

## Device

Support to the number of users, fingerprints, faces, and cards in Manage Users in
 Device

## Access Control

Support for a larger number of access groups and access groups

# Monitoring

Support to Graphic Map

# Time & Attendance

- Support to Working alarm time report
- Improve the process for generating the time card
- Support to the separator option in CSV export
- Support to Floating shift
- Support to Fixed option in Meal deduction and Break Time
- Support to Weekend days setting option in Schedule Template

### Setting

- Support to Custom Account Level in T&A
- Support to AES encryption type for DESFire card
- Support to DESFire Advanced option

# Compatible firmware

BioLite Net: 2.3.5 or later

- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.7.0 or later
- BioStation A2: 1.6.0 or later
- BioStation L2: 1.4.0 or later
- BioEntry W2: 1.3.0 or later
- FaceStation 2: 1.2.0 or later
- CoreStation: 1.2.0 or later
- BioEntry P2: 1.2.0 or later
- BioEntry R2: 1.2.0 or later
- BioLite N2: 1.1.0 or later
- XPass D2: 1.1.0 or later
- OM-120: 1.1.0 or later
- Secure I/O 2: 1.2.4 or later
- DM-20: 1.1.4 or later

New and improved features

Category

Functionality

## Setting

Support to set the same action for different triggers

#### Compatible firmware

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.4 or later
- BioEntry W: 2.3.4 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.6.2 or later
- BioStation A2: 1.5.1 or later
- BioStation L2: 1.3.2 or later
- BioEntry W2: 1.2.3 or later
- FaceStation 2: 1.1.1 or later
- CoreStation: 1.1.2 or later
- BioEntry P2: 1.1.2 or later
- BioEntry R2: 1.1.1 or later
- BioLite N2: 1.0.2 or later
- XPass D2: 1.0.2 or later
- OM-120: 1.0.0 or later
- Secure I/O 2: 1.2.1 or later
- DM-20: 1.1.2 or later

BioStar 2.6.3

New and improved features

Category

Functionality

Setting

Support Admin Item Settings when configuring Custom Account Level

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.3 or later
- BioEntry W: 2.3.3 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.6.1 or later
- BioStation A2: 1.5.1 or later
- BioStation L2: 1.3.1 or later
- BioEntry W2: 1.2.1 or later
- FaceStation 2: 1.1.1 or later
- CoreStation: 1.1.1 or later
- BioEntry P2: 1.1.1 or later
- BioEntry R2: 1.1.0 or later
- BioLite N2: 1.0.2 or later
- XPass D2: 1.0.1 or later
- OM-120: 1.0.0 or later

- Secure I/O 2: 1.2.1 or later
- DM-20: 1.1.2 or later

New and improved features

Category

Functionality

User

Support the user information export/import by using the external storage (USB)

Video

Support the real-time video monitoring

Monitoring

• Support the event log import by using the external storage (USB)

- BioLite Net: 2.3.5 or later
- BioEntry Plus: 2.3.3 or later

- BioEntry W: 2.3.3 or later
- Xpass: 2.4.4 or later
- Xpass S2: 2.4.4 or later
- BioStation 2: 1.6.1 or later
- BioStation A2: 1.5.1 or later
- BioStation L2: 1.3.1 or later
- BioEntry W2: 1.2.1 or later
- FaceStation 2: 1.1.1 or later
- CoreStation: 1.1.1 or later
- BioEntry P2: 1.1.1 or later
- BioEntry R2: 1.1.0 or later
- BioLite N2: 1.0.2 or later
- XPass D2: 1.0.1 or later
- OM-120: 1.0.0 or later
- Secure I/O 2: 1.2.1 or later
- DM-20: 1.1.2 or later

New and improved features

Category

Functionality

General

- Support the Daylight Saving Time(DST)
- Support the database encryption key management
- Support the system ports setting
- Support the system logs management
- Firmware upgrade notifications supported
- Change the license policy

# User & Card

- Support for the auto-Increase User IDs
- Support the iCLASS Seos card setting
- Support the hexadecimal values for the primary and secondary site keys on the smart card
- Wiegand card search supported from the Unassigned card menu
- Support for automatic deletion of user information when issuing an AoC card
- Wiegand Legacy Mode Support
- Blacklist card deletion support

### Device

- Support BioLite N2
- Support XPass D2
- Support BioMini Plus 2
- Support the user information and log deletion when a tamper event occurs (secure tamper)
- Device reset excluding network settings
- Wiegand In/Out Support

### Zone

- Support the interlock zone
- Support the muster zone

Video

- Support MS SQL for Video log
- Support the video file storage management

## Monitoring

Add door column to event log list

- BioLite Net: 2.3.3 or later
- BioEntry Plus: 2.3.3 or later
- BioEntry W: 2.3.3 or later
- Xpass: 2.4.3 or later
- Xpass S2: 2.4.3 or later
- BioStation 2: 1.6.0 or later
- BioStation A2: 1.5.0 or later
- BioStation L2: 1.3.0 or later
- BioEntry W2: 1.2.0 or later
- FaceStation 2: 1.1.0 or later
- CoreStation: 1.1.0 or later
- BioEntry P2: 1.1.0 or later
- BioEntry R2: 1.1.0 or later
- BioLite N2: 1.0.0 or later
- XPass D2: 1.0.0 or later
- OM-120: 1.0.0 or later
- Secure I/O 2: 1.2.1 or later
- DM-20: 1.1.2 or later

New and improved features

Category

Functionality

## General

- Setting https as the default communication protocol
- Oracle Database not supported

#### Device

- Supports CoreStation
- Supports BioEntry P2
- Supports BioEntry R2
- Supports the enrollment of a fingerprint from the slave device(BioLite Net does not support this feature)

Zone

Supports Intrusion Alarm zone (Local)

### Monitoring

- Event Log, Real-time Log: T&A Key column added
- Event Log: Supports the period setting
- Supports video log

Video

- Supports NVRs (ACTi, Dahua, Hikvision)
- Supports IP cameras

### Setting

- Alert: Network disconnection detection alert added
- Supports Audit Trail

## Compatible firmware

- BioLite Net: 2.3.3 or later
- BioEntry Plus: 2.3.3 or later
- BioEntry W: 2.3.3 or later
- Xpass: 2.4.3 or later
- Xpass S2: 2.4.3 or later
- BioStation 2: 1.5.0 or later
- BioStation A2: 1.4.0 or later
- BioStation L2: 1.2.3 or later
- BioEntry W2: 1.1.4 or later
- FaceStation 2: 1.0.3 or later
- CoreStation: 1.0.0 or later
- BioEntry P2: 1.0.0 or later
- BioEntry R2: 1.0.0 or later

BioStar 2.4.1

New and improved features

Category

### Functionality

#### General

Supports Mobile Card (NFC, BLE)

### Device

Supports FaceStation 2

### Time & Attendance

- Enhanced UI/UX
- Merge the time card with T&A report
- Display of daily T&A records
- Time rate setting is excluded from the time code for leave management.
- Break time is displayed on the time slot when fixed work is used.
- It is possible to set the Min. Duration and Punch in Time Limit when flexible work is used.

## Setting

Supports Face Group Matching

- BioLite Net: 2.4.0 or later
- BioEntry Plus: 2.4.0 or later
- BioEntry W: 2.4.0 or later

- Xpass: 2.4.1 or later
- Xpass S2: 2.4.0 or later
- BioStation 2: 1.4.0 or later
- BioStation A2: 1.3.0 or later
- BioStation L2: 1.2.2 or later
- BioEntry W2: 1.1.2 or later
- FaceStation 2: 1.0.0 or later

New and improved features

Category

### Functionality

General

- Supports elevator management
- Supporting Oracle Database 11g, 12c

Device

- Supports OM-120
- Supports card USB device (DUALi DE-620)
- Supports secure communication between BioStar 2 and a device

Time & Attendance

Supports time & attendance report PDF export

## Setting

- Change of detailed custom permission setting
- Supports user ID type setting (numbers/alphanumeric characters)
- Supports dd/mm/yyyy date format

## Compatible firmware

- BioLite Net: 2.4.0 or later
- BioEntry Plus: 2.4.0 or later
- BioEntry W: 2.4.0 or later
- Xpass: 2.4.0 or later
- Xpass S2: 2.4.0 or later
- BioStation 2: 1.4.0 or later
- BioStation A2: 1.3.0 or later
- BioStation L2: 1.2.2 or later
- BioEntry W2: 1.1.2 or later

BioStar 2.3.0

New and improved features

## Category

## Functionality

## General

- Supporting a low-resolution monitor
- Improvement in list page move

### User

Improvement importing/exporting CSV files

## Device

- Supporting BioStation A2 video phone (SIP based)
- Supporting the batch editing the device manager
- Supporting an additional information display of a device firmware

## Door

Supporting an automatic door setting

# Setting

- Supporting Wiegand card's facility code setting
- Supporting the batch editing the Wiegand card data format
- Supporting BioStar 2 alert sound's upload and setting (.wav, .mp3)
- Supporting the custom account level (up to 32)

- BioLite Net: 2.3.0 or later
- BioEntry Plus: 2.3.0 or later
- BioEntry W: 2.3.0 or later

- Xpass: 2.3.0 or later
- Xpass S2: 2.3.0 or later
- BioStation 2: 1.3.0 or later
- BioStation A2: 1.2.0 or later
- BioStation L2: 1.1.0 or later
- BioEntry W2: 1.0.0 or later

### New and improved features

BioEntry W2 support

- BioLite Net: 2.2.3 or later
- BioEntry Plus: 2.2.3 or later
- BioEntry W: 2.2.3 or later
- Xpass: 2.2.3 or later
- Xpass S2: 2.2.3 or later
- BioStation 2: 1.3.0 or later
- BioStation A2: 1.1.0 or later
- BioStation L2: 1.0.0 or later
- BioEntry W2: 1.0.0 or later

### New and improved features

- BioStation L2 support
- Long-term idle user management
- Access control privilege management per user
- Automatic database backup
- Enrollment device management
- Custom user fields

- BioLite Net: 2.2.3 or later
- BioEntry Plus: 2.2.3 or later
- BioEntry W: 2.2.3 or later
- Xpass: 2.2.3 or later
- Xpass S2: 2.2.3 or later
- BioStation 2: 1.3.0 or later
- BioStation A2: 1.1.0 or later
- BioStation L2: 1.0.0 or later

New and improved features

- BioStation A2 support
- Access On Card
- Secure Credential Card
- Global Anti-passback zone
- Image Log

Compatible firmware

- BioLite Net: 2.2.3 or later
- BioEntry Plus: 2.2.3 or later
- BioEntry W: 2.2.3 or later
- Xpass: 2.2.3 or later
- Xpass S2: 2.2.3 or later
- BioStation 2: 1.2.0 or later
- BioStation A2: 1.0.0 or later

BioStar 2.1.0

New and improved features

- BioStar API
- DM-20 support
- Global Anti-passback zone / Local Fire Alarm zone / Local Anti-passback zone
- More secure login password
- License management
- BioStar 2 Cloud support
- BioStar 2 Mobile support
- Zone status monitoring

### Compatible firmware

- BioLite Net: 2.0.4 or later
- BioEntry Plus: 2.0.4 or later
- BioEntry W: 2.0.4 or later
- Xpass: 2.0.4 or later
- Xpass S2: 2.0.4 or later
- BioStation 2: 1.0.1 or later

BioStar 2.0.1

## New and improved features

- BioStation 2 support
- Wireless LAN configuration

- T&A configuration
- Interphone configuration
- Display and sound configuration
- CSV import and export
- Multi-language resource support
- Memory optimization of BioStar 2 server

- BioLite Net: 2.0.0 or later
- BioEntry Plus: 2.0.0 or later
- BioEntry W: 2.0.0 or later
- Xpass: 2.0.0 or later
- Xpass S2: 2.0.0 or later